
LinkTenn32 Release Notes for Version 1.29.53

LinkTenn32 supports these process controllers for release 1.29.53

1. VersaTenn 3 /VersaTenn 2 /VersaTenn (VT3)
2. VersaTenn 4 (VT4)
3. VersaTenn 5 /Synergy Controller /Compatibles (VT5)
4. Watlow 942 (W942)
5. Watlow F4 (WF4)
6. Thermotron 4800 (T4800)
7. Partlow 1460/62 (P1460)
8. Yokogawa 550/750 (Y750)

What' s New

No new features added this release.

Bug Fixes

Fixes a channel two scaling display problem introduced when adding the Temperature Pressure configuration for VersaTenn 5 /Synergy Controller /Compatibles (VT5).

Known Issues

Aladdin Hasp Key Driver Issue.

After application installation completes and the Hasp key is inserted, the 'Add New Hardware wizard' may appear; this happens only on Windows XP with SP2 installed, the procedure outlined in Aladdin Hasp Key Driver Install Issue_D10122006 app note should be followed to complete Hasp key driver installation. There is an issue with the Aladdin driver installation program and this procedure must be completed so dongle key can be recognized. This procdure supercedes any previous instructions for Hasp driver installation where the 'Add New Hardware' wizard appears. This issue will resolved upon receiving a solution from Aladdin. This pertains to LinkTenn32 v1.27.50 and later.