
Synergy Manager Release Notes for v2.12.21

Synergy Manager supports these process controllers for v2.12.21

1. VersaTenn 3 /VersaTenn 2 /VersaTenn (VT3)
2. VersaTenn 4 (VT4)
3. VersaTenn 5 /Synergy Controller /Compatibles (VT5)
4. Watlow 942 (W942)
5. Watlow F4 (WF4)
6. Thermotron 4800 (T4800)
7. Partlow 1460/62 (P1460)
8. Yokogawa 550/750 (Y750)

What' s New

None this release see 'Bug Fixes'.

Bug Fixes

Fixes a bug with Yokagawa 750/550 events that prevents profiles from being downloaded with ramp times over 99 minutes.

Updates Aladdin driver install program to version 5.50 for Windows XP only.

Known Issues

Aladdin Hasp Key Driver Issue.

After application installation completes and the Hasp key is inserted, the 'Add New Hardware wizard' may appear; this happens only on Windows XP with SP2 installed, the procedure outlined in Aladdin Hasp Key Driver Install Issue_D10122006 app note should be followed to complete Hasp key driver installation. There is an issue with the Aladdin driver installation program and this procedure must be completed so dongle key can be recognized. This procdure supercedes any previous instructions for Hasp driver installation where the 'Add New Hardware' wizard appears. This issue will resolved upon receiving a solution from Aladdin. This pertains to Synergy Manager v2.09.50 and later.